

Table of Contents

- Conditions** 1
- Current Weather** 1
- Weather Themes** 1
- Weather Mode for Active Sky Weather Engine** 2
 - Change Weather Mode 3
 - Historic Dynamic Weather 3
- Real-Time Weather** 3
- Real-Time Weather for X-Plane** 4
 - Continous Real-Time Weather 5
- Weather Effects for Active Sky Weather Engine** 5
 - Weather Effect 6
 - General 7
 - Effect Altitude 8
 - Effect Location 8
 - Relative to Aircraft Location 8
 - Absolute Location 9
- ILS Visibility** 9
- Custom Weather** 10
 - Load and Send Weather 10
 - Add as Weather Preset 11
 - Wind Layers 11
 - Cloud Layers 12
 - Visibility Layers 14
 - Temperature Layers 14
 - Atmospheric Pressure 15
- Custom Weather for X-Plane** 15
 - Atmospheric Conditions 15
 - Thermals 16
 - Wind Layers 16
 - Bodies of Water 17
 - Cloud Layers 17
 - Runway Conditions 17
- Custom Weather for Active Sky Weather Engine** 18
 - Surface Wind 18
 - Surface Visibility 19
 - Wind Aloft Layers 19
 - Cloud Layers 20
 - Atmospheric Pressure 21
- Weather Presets** 22
 - Pop-Up Menu 22
 - Rename Weather Preset 22
- Season and Time** 23
 - Set Custom Date and Time 23
- Simulation Rate** 24
- General Info** 24

Conditions

Define and save detailed custom weather conditions, enable real-time weather, set ILS visibility for all categories and set season, time and simulation rate.

Current Weather

Current Weather

Current METAR: **EDDM&A453 300706Z 26010KT&D304NG 80000&B-1500&D2048 RA 4CU003&CU000FLLR000N 5CU007&CU000FMMN000N 6CU036&CU000FLMN000N 04/02&A0453 Q1033**

Translated to Text:


Show as Table
 Show Only
 Official METAR

Location	Weather station Munich, Munich, Germany (EDDM) in a height of 453 m
Report Date and Time	Wednesday, December 30, 2015 at 7:06:00 AM UTC
Surface Wind	With 10 kt from 260° true. The depth/height of the surface wind is 304 m.
Visibility	80.0 km in all directions
Weather	Moderate rain
Clouds Layer 1	Cumulus cloud coverage of 4 oktas at 300 ft. above aerodrome level. The tops of the clouds are flat. There are light turbulances in these clouds. There is light rain in these clouds. The icing rate is light.
Clouds Layer 2	Cumulus cloud coverage of 5 oktas at 700 ft. above aerodrome level. The tops of the clouds are flat. There are moderate turbulances in these clouds. The icing rate is moderate.
Clouds Layer 3	Cumulus cloud coverage of 6 oktas at 3,600 ft. above aerodrome level. The tops of the clouds are flat. There are light turbulances in these clouds. The icing rate is light.
Temperature	4°C with a dew point of 2°C up to an altitude of 453 m
QNH	1,033 hPa (mean sea level pressure)

Name:

In this section the current weather is displayed as METAR code and translated text.

You can choose if the translated text it displayed as continuous text or structured table. Additionally you can decide if all or only official weather METAR data is displayed.


 **Note:** The flight simulator uses the official METAR format, but extends is with additional extensions. FS-FlightControl can decode both, the official METAR data as well as the flight simulator extensions.

You can load the current weather into the [custom weather](#) section or save it as [weather presets](#).


Weather Themes




Here all themes that are available in the flight simulator are listed and can be activated with just one click.

 Note: This section does not appear if Active Sky is enabled as weather engine in the [Settings](#) module.


Weather Mode for Active Sky Weather Engine



In this area you can see the current Active Sky weather mode and change it, too.

 Note: This section only appears if Active Sky is enabled as weather engine in the [Settings](#) module.

Change Weather Mode



Change Weather Mode

Real-Time Live Weather

Locked to Simulator Time

Historic Dynamic Weather


24.11.2016 Time: 0 : 0

Custom Static Mode

Set Weather Mode

Select the desired weather mode here and set it with the button Set Weather Mode.

Historic Dynamic Weather




Historic Dynamic Weather

24.11.2016 Time: 13 : 30

If you have chosen the hisotoric dynamic weather mode you can set the historic date and time here.


Real-Time Weather



You have the option to enable real-time weather in this section.

Therefore you can either send the current real-time weather directly to flight simulator or load it into the [custom weather](#) section.

 Note: You can change the used real-time weather source in the [Settings](#) module.


 Note: This section does only appear if Prepar3D, FSX or FSW is selected as simulator type and Active Sky is not enabled as weather engine in the [Settings](#) module.

Real-Time Weather for X-Plane



You have the option to enable real-time weather in this section.

Additionally you will see the current availability status of the real-time weather and you have the option to use the button `Refresh Real-Time Weather Now` to reload the weather at any time.

 Note: This section does only appear if X-Plane is selected as simulator type.

Continous Real-Time Weather

Continous Real-Time Weather

Automated Weather Update (whatever is first):

Every Certain Time: sec.

After Flown Distance: NM

No Weather Update Below Altitude Above Ground: ft.

Next Automated Update:

Either in: **101 sec.**

Or After: **10 NM**

To enable continues real-time weather just activate the corresponding check box. This will enable automated real-time weather updates for all weather stations around the current aircraft location.

You can choose how often this weather update should be performed by entering a certain time interval or a flown distance (or both).

Additionally you can define that automated weather updates should not be performed when the aircraft is below a certain altitude above ground. This makes sure that the pilot is not disturbed while doing a final approach.

Below that some information is displayed to show when the next automated weather update will be performed.

Weather Effects for Active Sky Weather Engine

Weather Effects for Active Sky Weather Engine

Existent Weather Effects:

Weather Effect

General

Unique Identifier:

Effect Type:

Effect Intensity: ft/min.

Effect Location

At Current Aircraft Location

Relative to Aircraft Location

Bearing: Current Aircraft Bearing

Custom: °

Distance: NM

Absolute Location

Latitude: °

Longitude: °

Location Range: ft


Effect Altitude

Current Aircraft Altitude


Custom MSL: ft

Altitude Range: ft

In this area you can create new and edit existent Active Sky weather effects.


 Note: This section only appears if Active Sky is enabled as weather engine in the [Settings](#) module.

Weather Effect




Here different options of the weather effect can be changed.

Use the button `Send New Effect to Active Sky` to active a new weather effect, the button `Delete Effect` to remove an existent one again and `Copy Effect` to create a duplicate of the current selected effect.

 **Note:** An already sent weather effect cannot be changed anymore. Please just duplicate it and then remove the old one.

General




First you can enter a name for the weather effect here and set the effect type as of

- Thermal
- Downdraft
- Updraft
- Turbulence
- Windshear

Then the effect intensity can be defined as vertical speed for thermal, downdraft and updraft effect types and as an intensity between 1 and 5 for the turbulence and windshear effect types.


Effect Altitude



You can choose here if the current aircraft altitude should be used for the effect or you want to define an altitude (MSL) manually.

Additionally an altitude range can be set: So if you define, for example, an custom altitude of 10,000 ft and an altitude range of 1,000 ft the effect will be active between 9,500 and 10,500 ft.


Effect Location



Select here if the effect should be placed at the current aircraft location, relative to the aircraft location or at a custom absolute location.

Additionally a location range can be set defining the radius around the location where the effect should be active.


Relative to Aircraft Location



If the effect should be placed relative to the aircraft location, you first need to choose if it should be placed in the direction of the current aircraft bearing or in a custom direction.


Then you need to define the distance the effect should be placed away from the aircraft.

Absolute Location



In case of an absolute position you can directly enter the latitude and longitude of the position where the weather effect should be located.

ILS Visibility



Use this section to set a pre-defined visibility condition for any of the ILS categories.

Following values are the default for decision height and runway visibility:

	Decision Height	Runway Visibility
CAT I	200 ft (60 m)	1,800 ft (550 m)
CAT II	100 ft (30 m)	1,000 ft (300 m)
CAT IIIa	50 ft (15 m)	600 ft (180 m)
CAT IIIb	30 ft (10 m)	150 ft (46 m)
CAT IIIc	0 ft (0 m)	30 ft (10 m)

 Note: You can customize these values in the [Settings](#) module to your needs.

Custom Weather

Custom Weather

METAR: Name:

Surface Wind

Wind Layer

Direction: °

Entirely Variable Direction

Variation from ° to °

Speed: kt

Gust Speed: kt

Surface Wind

Depth/Height: ft

Max. Altitude: ft

Turbulence:

Wind Shear:

39,300 - 40,940 ft.

Cloud Layer

Base Altitude: ft.

Cloud Coverage:

Cloud Type:

Top of Cloud:

Turbulence:

Precipitation:

Type of Precipitation:

Precipitat. Base Height: ft.

Icing Rate:

72 - 10,072 ft.

Visibility Layer

Base Altitude: ft.

Max. Altitude: ft.

Visibility: NM

Direction:

Atmospheric Pressure

Pressure: hPa

0 ft.


Temperature Layer

Max. Altitude: ft.

Temperature: °C

Dew Point: °C

In case you want to define a completely custom weather situation you can do so in this section.

 Note: This version of the custom weather section appears if Prepar3D, FSX or FSW is selected as simulator type.

Load and Send Weather

METAR:

If you have a METAR string as starting point for your custom weather enter it in the corresponding text field on top of the screen and click on the Load button. This will decode the weather situation defined in the METAR string into the custom weather sections below.


To send the weather define in these custom weather sections to the flight simulator, just click on the Send Weather button.

Add as Weather Preset



You may also save your custom weather situation as [weather presets](#). Just enter a name and then click on the Add Preset button.

Wind Layers



You can define all wind layers - including the surface wind - in this section.

First you can define the direction where the wind is coming from. You have two additional options regarding the wind direction:

You can define it as Entirely Variable or even enter the from and to direction where the wind is coming from. If the wind should come only from a fixed direction, just keep the Entirely Variable Direction check box unchecked and the variation input fields as .

Next enter the speed and optional gust speed (keep it if not needed) of the wind layer.

Next you can define if the current wind layer is a surface wind or an wind aloft. In case of a surface wind you have the additional option to define a depth/height of the wind and if it is a wind aloft you can define a maximum altitude (MSL) for it instead.

 Note: You may add as many wind layers as you want, but there can be only one of them defined as

surface wind.

Finally you can define turbulences in this wind layer as

- None
- Light
- Moderate
- Heavy
- Severe

and wind shears as:

- Gradual (none)
- Moderate
- Steep
- Instantaneous

Cloud Layers

39,300 - 40,940 ft. +

Cloud Layer

Base Altitude: 39,300 ft.

Cloud Coverage: 6/8 Coverage

Cloud Type: Cirrus

Top of Cloud: Flat

Turbulence: None

Precipitation: Moderate

Type of Precipitation: None

Precipitat. Base Height: 0 ft.

Icing Rate: None

Delete Layer

Here you can define all cloud layers of the custom weather situation.

First enter a base altitude (MSL) for the cloud layer.

Then you can define several additional parameters for like cloud coverage as of

- Few Clouds
- Scattered Clouds
- Broken Clouds
- Overcast
- 1/8 Coverage
- 2/8 Coverage
- 3/8 Coverage

- 4/8 Coverage
- 5/8 Coverage
- 6/8 Coverage
- 7/8 Coverage
- 8/8 Coverage

cloud type as of

- Cirrus
- Stratus
- Cumulus
- Cumulo-nimbus

top of the cloud as of

- Flat
- Round
- Anvil

turbulences in the cloud layer as of

- None
- Light
- Moderate
- Heavy
- Severe

type of precipitation as of

- None
- Rain
- Freezing Rain
- Hail
- Snow

precipitation strength as of

- Very Light
- Light
- Moderate
- Heavy
- Dense

the base altitude of the precipitation as well as the icing rate as of

- None
- Trace
- Light
- Moderate
- Severe

Visibility Layers

72 - 10,072 ft. +

Visibility Layer

Base Altitude: 72 ft.

Max. Altitude: 10,072 ft.

Visibility: 54.00 NM

Direction: All

Delete Layer


The visibility layers of the custom weather situation can be defined in this section.

First enter the base and maximum (top) altitude (MSL) of the visibility layer.

Then you can define the visibility in this layer itself.

Finally you can decide in which direction this visibility should be effective as of

- All
- North-West
- North
- North-East
- East
- South-East
- South
- South-West
- West

 Note: To set the same visibility for more than one direction, but not for all, just create another visibility layer with the same base and maximum altitude.

Temperature Layers

0 ft. +

Temperature Layer

Max. Altitude: 0 ft.

Temperature: 25 °C

Dew Point: 1 °C


Delete Layer

Also individual temperature layers can be defined for your custom weather situation.

First enter the maximum altitude (MSL) up to which this layer should be valid.


Then you can enter the temperature and dew point of this temperature layer.

Atmospheric Pressure




Here you can define the atmospheric pressure for your custom weather situation.


Custom Weather for X-Plane



In case you want to define a completely custom weather situation you can do so in this section.


 Note: This version of the custom weather section appears if X-Plane is selected as simulator type.

Atmospheric Conditions




Here you can first define the visibility followed by the precipitation and storminess as percentage. Additionally the temperature, dew point and atmospheric pressure can be set.

Thermals



You can define thermal effects in this section. First enter the altitude where the thermal effect should occur. Then you can set its coverage as percentage as well as the climb rate.

Wind Layers




You can define all wind layers in this section.

First enter the direction, altitude and speed of the wind layer.

Next you can define the turbulence intensity between and 10.


Finally the gust direction change and speed increase can be set.

Bodies of Water



In this section the water wave height and direction can be defined.

Cloud Layers



Here you can define all cloud layers of the custom weather situation.

First choose the cloud type as of

- Cirrus
- Few Cumulus
- Scattered Cumulus
- Broken Cumulus
- Overcast Cumulus
- Stratus

Then you can enter a base and top altitude (MSL) for the cloud layer.

Runway Conditions




Here you can choose the runway conditions as of


- Dry
- Damp
- Wet

If you have chosen Damp or Wet you can additionally decide if the runway surface should be patchy or not.

Custom Weather for Active Sky Weather Engine



In case you want to define a completely custom weather situation you can do so in this section.

 Note: This version of the custom weather section only appears if Active Sky is enabled as weather engine in the [Settings](#) module.

Surface Wind

Surface Wind

Direction: 0 °

Variance: 0 °

Wind Speed: 0 kt

Gust Speed: 0 kt

Temperature: 25 °F

Dew Point: 1 °F

Turbulence: None ▼

You can define the surface wind in this section.

First you can define the direction where the wind is coming from including a variance.

Next enter the speed and optional gust speed (keep it if not needed) of the wind.

Also the temperature and the dew point on the surface can be defined here.

Finally you can define turbulences in the surface wind as:

- None
- Light
- Moderate
- Heavy
- Severe

Surface Visibility

Surface Visibility

Base Altitude: 72 ft

Max. Altitude: 10,072 ft

Visibility: 50,000 m

The surface visibility of the custom weather situation can be defined in this section.

First enter the base and maximum (top) altitude (MSL) of the visibility layer.

Then you can define the visibility itself.


Wind Aloft Layers

You can define all wind aloft layers in this section.

First enter the direction and speed of the wind layer.

Next you can define the temperature and finally the turbulences in this wind layer as:

- None
- Light
- Moderate
- Heavy
- Severe

 Note: The altitudes of the individual wind layers cannot be changed for Active Sky.

Cloud Layers

Here you can define all cloud layers of the custom weather situation.

First enter a base and top altitude (MSL) for the cloud layer.

Then you can define several additional parameters for like cloud coverage as of

- 1/8 Coverage

- 2/8 Coverage
- 3/8 Coverage
- 4/8 Coverage
- 5/8 Coverage
- 6/8 Coverage
- 7/8 Coverage
- 8/8 Coverage

cloud type as of

- Cirrus
- Stratus
- Cumulus
- Cumulo-nimbus

turbulences in the cloud layer as of

- None
- Light
- Moderate
- Heavy
- Severe

type of precipitation as of

- None
- Rain
- Freezing Rain
- Hail
- Snow


precipitation strength as of

- Very Light
- Light
- Moderate
- Heavy
- Dense

as well as the icing rate as of

- None
- Trace
- Light
- Moderate
- Severe

Atmospheric Pressure



Here you can define the atmospheric pressure for your custom weather situation.

Weather Presets




All your saved weather presets are listed here. There is no limit in the number of weather presets you can define.

Pop-Up Menu




If you right click (long “touch”) on a weather preset this pop-up menu will be shown enabling you to rename, delete or edit an existent weather preset again.

Rename Weather Preset



Here you can set a new name for an existent weather preset.


Season and Time



In this section you have a quick and easy control of the current season.


Just click on one of the pre-defined season buttons.

Set Custom Date and Time



Additionally you can define a completely custom date and time in this section.

Simulation Rate



Beside a very detailed weather configuration system this module offers here also an easy way to change the current simulation rate of the simulator.

Only for X-Plane additionally the actual simulation rate is shown next to the currently requested one. For Prepar3D, FSX and FSW these two are always identical.

General Info



Additionally in the bottom right of the screen you always have an eye on the current frame rate and simulator time.

FS-FlightControl Manual:
<https://www.fs-flightcontrol.com/en/manual/>

PDF Generated on:
2017/08/07 06:05

